ProSystem *fx* PDFlyer (Standalone)

Welcome to ProSystem *fx* PDFlyer (Standalone) 10.1

This bulletin provides important information about ProSystem *fx* PDFlyer (Standalone) 10.1. Please review this bulletin carefully. If you have any questions, contact Customer Support at 1-800-PFX-9998 (1-800-739-9998), Option 6. Additional information is available on CCH Support Online.

ProSystem *fx* PDFlyer 10.1 Enhancements

Icons have been updated to provide improved usability and readability.

Calculator tape print size can now be reduced by eliminating the section column and section title row. PDFlyer is set to print this information by default. To not print the section column or title row, clear the appropriate box in Settings > Calculator.

Insert PDF now remembers the last used file location and does not display a file name until a file has been selected.

The Acrobat bookmark pane now displays and bookmarks are expanded when any PDF file containing bookmarks is opened if the Expand Bookmarks on Open option is selected. The bookmark pane will not automatically display if the PDF file does not contain bookmarks. The bookmark pane may still be expanded or collapsed manually.

Bookmarked PDF files not produced by Scan now retain their bookmarks when merged or appended to an existing PDF file.

Bookmarks will inherit the appropriate color after moving from the child level to the parent level. It is still necessary to Colorize/Uncolorize Bookmarks for the updated bookmark color to display.

Set Status time stamps will now display leading zeroes for minutes and seconds.

Stamp colors now consistently update when using the Stamp Color feature.

Icons added to the Acrobat Quick Tools toolbar after upgrading to PDFlyer 10.0 will now make optimal use of available unused space on the toolbar.

Installing ProSystem *fx* PDFlyer (Standalone)

Installation Instructions

For detailed installation instructions, please refer to the ProSystem *fx* PDFlyer (Standalone) 10.0 User Guide. Brief instructions have been included below for your reference.

Installing ProSystem *fx* PDFlyer Server

If ProSystem *fx* PDFlyer Server is currently installed, manually remove the previous version. Install ProSystem *fx* PDFlyer Server to a network drive or shared local drive available to all workstations using ProSystem *fx* PDFlyer.

The following steps will guide you through the installation of ProSystem *fx* PDFlyer Server:

1. Download **PDFlyer Standalone.zip** here.
2. Extract and launch **PDFlyer Server.exe**. The installation wizard displays.
3. Click **Next**.
4. Review the License Agreement and accept the terms of the agreement.
5. Click **Next**.
6. To change the destination folder where ProSystem *fx* PDFlyer Server will be installed, click **Browse** and navigate to or enter a new location.
7. Click **Next**.

8. Choose the appropriate permission key option.
9. Click **Next**.
10. Click **Install**. Wait for the installation to complete.
11. Click **Finish**.

Installing ProSystem *fx* PDFlyer

Install ProSystem *fx* PDFlyer on workstations licensed for Adobe Acrobat Standard or Professional, version X or higher. ProSystem *fx* PDFlyer will not run with Adobe Reader.

Microsoft .NET Framework 2.0 and 4.0 must be installed on each workstation running ProSystem *fx* PDFlyer. If you have not already installed .NET Framework 2.0 and 4.0, they will be installed for you during the installation.

The following steps will guide you through the installation of ProSystem *fx* PDFlyer:

1. Browse to \\<computer name>\Workstation and launch **PDFlyer.exe** file. The installation wizard displays.
2. Click **Next**.
3. Review the License Agreement and accept the terms of the agreement.
4. Click **Next**.
5. If needed, change the destination folder where ProSystem *fx* PDFlyer will be installed by clicking **Browse** and navigating to or entering a new location.
6. Click **Next**.
7. Click **Install**. Wait for the installation to complete.
8. Click **Finish**.